

# Math 259A Lecture 1 Notes

Daniel Raban

September 27, 2019

## 1 Introduction to Operator Algebras

### 1.1 \*-algebras

Let  $H$  be a Hilbert space. We denote  $B(H)$  to be the space of operators on  $H$ :  $B(H)$  is the set of  $T : H \rightarrow H$  such that  $\sup_{\xi \in (H)_1} \|T(\xi)\| =: \|T\| < \infty$ , where  $(H)_1$  is the closed unit ball.  $B(H)$  is an algebra.

**Definition 1.1.** An **operator algebra** is a vector subspace  $B \subseteq B(H)$  closed under multiplication.

Given an operator  $T$ , we have an **adjoint operator**  $T^*$  which satisfies  $\langle T^*\xi, \eta \rangle = \langle \xi, T\eta \rangle$  for all  $\xi, \eta \in H$ . The adjoint has  $\|T^*\| = \|T\|$ . This defines an operation  $*$  :  $B(H) \rightarrow B(H)$  sending  $T \mapsto T^*$ . The  $*$  operation satisfies

- $(T + S)^* = T^* + S^*$
- $(\lambda T)^* = \bar{\lambda}T^*$
- $(TS)^* = S^*T^*$
- $(T^*)^* = T$ .

**Definition 1.2.**  $B \subseteq B(H)$  is a **\*-algebra** of operators on  $B(H)$  if it is closed under the  $*$  operation.

**Example 1.1.** Look at  $B(\ell_\infty^2) = M_\infty(\mathbb{C})$ .  $\ell_\infty^2$  has an orthonormal basis  $e_i$  with  $(e_i)_j = \delta_{i,j}$ . Elements of  $B(\ell_\infty^2)$  can be multiplied like infinite matrices, and the entries can be determined by this orthonormal basis.

We always consider algebras with a unit. So  $B \subseteq B(X)$  will always contain the element  $1_B = \text{id}_X \in B$ .

## 1.2 von-Neumann algebras and group von-Neumann algebras

**Definition 1.3.** A **von-Neumann algebra** is a  $*$ -algebra  $B \subseteq B(X)$  closed in the weak operator topology given by the seminorms  $p_{\xi, \eta}(T) = |\langle T\xi, \eta \rangle|$  ( $T_i \rightarrow T$  in the weak operator topology if  $\langle T_i(\xi), \eta \rangle \rightarrow \langle T(\xi), \eta \rangle$  for all  $\xi, \eta \in X$ ).

**Example 1.2.**  $B(X)$  is a von-Neumann algebra.

**Definition 1.4.** An operator  $U \in B(X)$  is **unitary** if  $U^* = U^{-1}$ .

**Example 1.3.** A representation  $\pi : \Gamma \rightarrow B(X)$  of a group  $\Gamma$  is called **unitary** if  $\pi(g)$  is unitary for all  $g \in \Gamma$ . If  $\pi$  is unitary, then  $\text{span } \pi(\Gamma)$  is a  $*$ -algebra on  $X$ . Then the closure of this space under the weak operator topology is a von-Neumann algebra.

Denote  $\ell^2(I)$  as  $\ell^2$  with an orthonormal basis indexed by  $I$ .

**Example 1.4.** Define the following representations of  $\Gamma$

1. The **regular representation** is  $\lambda : \Gamma \rightarrow U(\ell^2(\Gamma))$  is  $\lambda(g)\xi_h = \xi_{gh}$
2. Alternatively, right group multiplication induces the unitary representation  $\rho : \Gamma \rightarrow U(\ell^2(\Gamma))$  given by  $\rho(g)\xi_h = \xi_{hg^{-1}}$ .

Observe that  $[\lambda(g_1), \rho(g_2)] = 0$ . Let  $L(\Gamma)$  be the weak operator topology closure of  $\text{span}(\lambda(\Gamma))$ , and let  $R(\Gamma)$  be the weak operator topology closure of  $\text{span}(\rho(\Gamma))$ . These are **left and right group von-Neumann algebras**. One avenue of study to study the map  $\Gamma \mapsto L(\Gamma)$ .

This has many applications. These operators arising from groups are related to dynamics and ergodic theory.

## 1.3 Factors and $C^*$ -algebras

**Definition 1.5.** A von-Neumann algebra  $M$  is a **factor** if  $Z(M) = \mathbb{C}1$ , where  $Z$  denotes the center of the algebra.

**Example 1.5.**  $B(X)$  and  $L(\Gamma)$  are factors.

Here is a question that appeared early in the theory of von-Neumann algebras: Are there any other von-Neumann factors than  $B(X)$ ?<sup>1</sup> This is fundamental to understanding how much commutation there is in operator algebras. The answer is yes. In fact,  $L(\mathbb{F}_2)$  and  $L(S_\infty)$  are not isomorphic to  $B(X)$ .

---

<sup>1</sup>von-Neumann asked this question in 1935. He gave this question to a postdoc. Prior to this, he knew that any von-Neumann algebra decomposes via a measurable field of matrices as  $M \cong \int_X M_t dt$ . They solved the problem in 1936.

These two are infinite dimensional factors, and they have a trace functional on them,  $\tau : M \rightarrow \mathbb{C}$  which is linear and continuous such that  $\tau(x, y) = \tau(yx)$  for all  $x, y \in M$ . In general, if  $X$  is infinite dimensional,  $B(X)$  has no trace defined everywhere.

Another question: Can we axiomatize the theory of von-Neumann algebras? We have a Banach-algebra with the  $*$ -operation, and we have the norm with  $\|T^*\| = \|T\|$ . Can we construct a Hilbert space only from this information?<sup>2</sup>

**Definition 1.6.** A  $*$ -algebra  $B \subseteq B(X)$  of operators on  $X$  is called a **(concrete)  $C^*$ -algebra**.

In fact, these satisfy  $\|T^*T\| = \|T\|^2$  for all  $T$ . (This does imply that  $\|T^*\| = \|T\|$ .)

**Definition 1.7.** A Banach algebra with  $*$  satisfying  $\|x^*x\| = \|x\|^2$  is called an **abstract  $C^*$ -algebra**

**Theorem 1.1** (G-N + Segal, 1943). *If  $B$  is an abstract  $C^*$  algebra, then it is a concrete  $C^*$ -algebra.*

---

<sup>2</sup>Gelfand and Naimark worked on this in 1940-1943. They did not succeed, and Grothendieck tried in the 50s.